Set command

```
set,relayx,status
Range:
    x = 1, 2, 3 or 4
    status = on/off
Example:
    set,relay1,on ← turn on relay 1
    set,relay1,off ← turn off relay 1
```

Repeat command

Repeat, relayx, initial State, time On, Time Off, repeat Cycles Range:

```
x = 1, 2, 3 or 4
initialState = on/off
timeOn = time in milliseconds
timeOff = time in milliseconds
repeatCycles = complete cycles (0 to infinite cycles)
Example:
```

repeat,relay1,on,1000,2000,0 ← Infinites cycles with 1000 ms turn on and 2000 ms turn off. Start with state on.

repeat,relay2,off,1000,2000,5 ← 5 cycles with 1000 ms turn on and 2000 ms turn off.

Start with state off.

OBS

Commands must be sent with \r\n and must have all lowercase characters (case sensitive).